

This course material is free: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation. It is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

More details about the GNU General Public License can be seen at:
<<http://www.gnu.org/licenses/>>.

Tutorial: BwUniCluster 2.0/HoreKa Modules

In this tutorial we will learn about modules and how to utilize them on the BwUniCluster or HoreKa

1. What are modules?

Modules are means by which the user can access and use the software installed on the BwUniCluster or HoreKa such as widely used compilers and software. In order to use a specific program or software (eg. OpenFOAM) the user has to load in the corresponding module during their session.

2. How to find and load specific module?

You can view the list of all available modules using the following command:

```
$> module av
```

or

```
$> module spider openfoam
```

The modules can be then loaded in using the following command:

```
$> module load [name of the module]
```

For example:

```
$> module load cae/openfoam/v2106-impi
```

The compiler then generates the following response:

```
////////////////////////////////////  
Don't forget to initialize OpenFOAM with:
```

```
source $FOAM_INIT
```

or simply:

```
foamInit
```

```
////////////////////////////////////
```

After initializing OpenFOAM we can use it like we would on a personal computer. However, we need to remember that a module initialized this way can only be used on the current terminal i.e. opening a second terminal does not mean that the modules loaded on the first terminal will be available in the second one. The same is valid for the compute nodes – before running OpenFOAM on a compute node we have to load the modules anew. In order to use a module on the computing node we need to load it using the batch job command (in blue). For example (the job-example here is not parallel):

```
////////////////////////////////////  
#!/bin/bash  
  
#SBATCH --partition dev_single  
#SBATCH --nodes=1  
#SBATCH --ntasks=1  
#SBATCH --time=00:30:00  
#SBATCH --mem=8000mb  
#SBATCH --job-name=MyFirstParallelJob  
  
module purge  
module load cae/openfoam/v2106-impi  
source $FOAM_INIT  
  
pimpleFoam  
////////////////////////////////////
```

3. How to remove installed modules?

To see what modules you have currently loaded (some of them are loaded automatically when you login) use the command:

```
$> module list
```

In order to remove the already loaded modules (all of them) we can use the following command:

```
$> module purge
```

To remove only one module, e.g. the module `system/ssh_wrapper/0.1` use:

```
$> module unload system/ssh_wrapper/0.1
```